



Article published on February 5th 2012 | [Software](#)

If you want to share your music, picture or anything within your personal computer and you found it difficult then you can use window7 homegroup to simplify this type of work like sharing, music, picture and other material that you have kept in your computer. You can share all these type of data with the help of window7 homegroup. If you want to share your USB printer you can also take the help of Window7 homegroup, the printer will installed automatically if there is window7 homegroup installed in other computer from where you want to share the documents.

There are some steps by which we can configure the printer are following:-

We have to go to network and sharing centre then after selecting homegroup we have to go to sharing option and there we have to change the advance sharing settings and then under the section of home and work selection then we has to select some options

We have to on the network discovery; there we will have to on the file and printer sharing, to connect to the other network then save the changes. We also need to sure that both printers are in the same group.

After all these steps we can install the printer on the personal computer on the homegroup network window7.

Now if we want to share anything, like pictures, music, documents or anything from one computer to other computer by homegroup.

It has been designed by Microsoft to be easy to add a network printer to a homegroup network by using Windows7. With the help of HomeGroup networking, whenever the user add or install the printer to the computer, the home network recognizes it automatically and adds it to the device stage on every computer in the HomeGroup.

With Windows7, you can have both regular networks and HomeGroup networks. As long as a printer is attached to a computer within your network, you can also add it to the homegroup, if the computer itâ€™s attached to isnâ€™t going to be part of the HomeGroup.

While creating a Windows7 homegroup and attempting to print your homegroup password, Windows may return an error status:

Your homegroup password couldn't be printed

an error had interrupted in the system . (Error code: 2147500057)

If the internet browser is not your current or the default browser you have to face this problem. If you want to fix this error, and allow you to print your home group password, you have to set Internet Explorer as your default web browser.

Article Source:

<http://www.articleside.com/software-articles/how-to-print-in-a-home-group-network.htm> - [Article Side](#)

[Theodore Sumrall](#) - About Author:

Theodore Sumrall is a professional content writer working with Icybergenie.com which provides 24 x7 online technical supports for computer users. Learn about a [how to remove virus form computer](#) and a [Upgrade Internet Explorer](#).

Article Keywords:

Upgrade Internet Explorer, How to Remove Virus

You can find more [free articles](#) on [Article Side](#). Sign up today and share your knowledge to the community! It is completely FREE!